

Software Product Compatibility Reports
Detailed System Requirements

IBM SPSS Statistics 31.0.1.0

# **Operating Systems**

The Operating sysytems section specifies the operating systems that IBM SPSS Statistics 31.0.1.0 supports, organized by operating system familiy.

## Operating system families

Windows

Component support			
	Full		
	Partial		

None

## **Windows**

## Summary

Operating system	Operatin system minimun	Hardware	Bitness	Product minimum	Components 👤 🗓	Notes?
Windows 10 Education	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• 0	No
Windows 10 Enterprise	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• 0	No
Windows 10 Home	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• 0	No
Windows 10 Pro	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• 0	No
Windows 11 Enterprise	Base	x86-64	64-Exploit	31.0.1.0	• 0	No
Windows 11 Pro	Base	x86-64	64-Exploit	31.0.1.0	• 0	No

Operating system	Operatin system minimum	Hardware	Bitness	Product minimum	Components 👤 🗓	Notes?
Windows Server 2012 R2 Datacenter Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2012 R2 Essentials Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2012 R2 Standard Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2016 Datacenter Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2016 Essentials Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2016 Standard Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2019 Datacenter Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2019 Essentials Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2019 Standard Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2022 Datacenter Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes
Windows Server 2022 Datacenter: Azure Edition	Base	x86-64	64- Exploit,64- Tolerate	31.0.1.0	• •	Yes



Operating system	Operatin system minimun	Hardware	Bitness	Product minimum	Components	Notes?
Windows Server 2022 Standard Edition	Base	x86-64	64-Exploit	31.0.1.0	• •	Yes

## Windows Notes

- 1. If Statistics Desktop or Statistics Developer is installed on a supported Windows Server operating system, it must use a Concurrent License.
- 2. If Statistics Desktop or Statistics Developer is installed on a supported Windows Server operating system, it must use a Concurrent License.

# Hardware

IBM SPSS Statistics 31.0.1.0 requires the following hardware organized by operating system family.

# **Operating System Families**

Windows

### **Windows**

Hardware	Components	Requirement	Applicable operating systems
Disk Space	Desktop  IBM SPSS Statistics Client  Server  IBM SPSS Statistics Server	4 gigabytes (GB) of available hard-disk space.	All supported Windows operating systems
Display	Desktop  IBM SPSS Statistics Client  Server  IBM SPSS Statistics Server	1024*768 or higher screen resolution	All supported Windows operating systems
Memory	Desktop  IBM SPSS Statistics Client  Server  IBM SPSS Statistics Server	4 gigabyte(GB) of RAM or more is required, 8 gigabyte(GB) of RAM or more is recommended for 64-bit Client platforms.	All supported Windows operating systems

Hardware	Components	Requirement	Applicable operating systems
Network: adapters, drivers, protocols	<ul> <li>Desktop</li> <li>IBM SPSS         Statistics Client</li> <li>Server</li> <li>IBM SPSS         Statistics         Server</li> </ul>	IPv6 is supported and it is not required.	All supported Windows operating systems
Processor	<ul> <li>Desktop</li> <li>IBM SPSS         Statistics Client</li> <li>Server</li> <li>IBM SPSS         Statistics         Server</li> </ul>	1.6 GHz or faster	All supported Windows operating systems
Product specific	• IBM SPSS Statistics Client Server • IBM SPSS Statistics Server	For Linux Server: Minimum free disk space: 1.5 gigabyte (GB) for installation. Because the installer extracts files before installing, the same amount of temporary disk space is also needed for the installer. If you do not have enough space in /tmp or the installing user's home directory, use the IATEMPDIR environment variable to specify a different temporary location for the extracted installer files. You can remove this folder after installation. Additional free disk space is required to run the program (for temporary files). The amount of space needed for temporary files depends on the number of users, the expected size of the .sav file, and the procedure. You can use the following formula to estimate the space needed: <number of="" users=""> * &lt;.sav file size&gt; * <factor for="" procedures="">, where <factor for="" procedures=""> can range from 1 to 2.5. For example, for procedures like K-Means Cluster Analysis (QUICK CLUSTER), Classification Tree (TREE), and Two-Step Cluster Analysis (TWOSTEP CLUSTER), the <factor for="" procedures=""> is closer to 1 than 2.5. If sorting is involved, it is 2.5. So, if you have four users, the expected .sav file size is 100 MB, and sorting is involved, you should allow 1 GB (4 x 100 MB x 2.5) of storage for temporary files.</factor></factor></factor></number>	All supported Windows operating systems

# Glossary

#### **Bitness**

Compatibility of the product with the bit version support that is provided by an operating system. Different parts of a product might run on the same operating system but support different application bitness. For example, one part of the product might run only in 32-bit mode, whereas another might support 64-bit tolerate mode.

**31:** The product or part of the product runs as a 31-bit application in a 31-bit operating environment.

**32:** The product or part of the product runs as a 32-bit application in a 32-bit operating environment.

**64-tolerate:** The product or part of the product runs as a 32-bit application in a 64-bit operating environment.

**64-exploit:** The product or part of the product runs natively as a 64-bit application in a 64-bit operating environment.

### Co-packaged

Additional products that are included in the product package.

### Co-installed

Additional products that are included in the product package and installed when the product is installed.

### **Deployment unit**

**Deployment Structure** identifies pieces of a product that can be independently deployed onto one or more machines in a distributed infrastructure.

- The top level of the deployment structure consists of one or more deployment units. There are four possible deployment units that a product might support: Desktop, Server, Agent or client, Mobile.
- Deployment units may be further divided into deployable components

**Desktop** deployment unit: Part of the deployment structure intended for use by a single user, typically installed on the user desktops. Examples of desktop deployment units include development tools, administrative tools, stand-alone business applications.

**Server** deployment unit: Part of the deployment structure that can provide services to multiple clients, providing the server in a client-server architecture. Examples of server deployment units include application servers, management servers, database servers and server-based business applications.

**Agent or client** deployment unit: Part of the deployment structure that allows remote connection between software. Examples of agent of client deployment

**Continuous Delivery** 

**Continuous Delivery** 

**Product - Long Term** 

**Support Release** 

**Product** 

	<b>Mobile</b> deployment unit: Part of the deployment structure intended for use by a single user, typically installed on a mobile device. An example of a mobile deployment unit is a mobile application.
Hypervisor	A virtual machine in which a product can run on a guest operating system.
Limited operating system support	By default, the supported guest operating systems for a product and a hypervisor are the operating systems that are supported by both the product and the hypervisor. If a product restricts support to a subset of these operating systems, this restriction will be indicated by specifying that there is Limited Operating System Support.
Operating system minimum	The minimum operating system maintenance level that is required to run on the product.
Prerequisite minimum	The minimum maintenance level that is required for the prerequisite to work with the product.
Product minimum	The minimum maintenance level that is required for the product to run on the operating system, on an hypervisor, or work with a prerequisite product or supported software.
Supported software minimum	The minimum maintenance level that is required for the supported software to work with the product.
Long Term Support Release	A Long Term Support Release is a recommended product level for which support, including defect and security updates, will be provided over a specified period of time.

installed with the software accessing the remote services.

units include agents in management system that are installed in the same tier as the managed resources, a remote application, or database clients that are

A Continuous Delivery Product delivers new function to clients more frequently.

A Continuous Delivery Product delivers new function to clients more frequently.

Since frequent releases may not be suitable for all client environments, Long

Term Support Releases provide a package that will be supported for a longer

Report data as of 28

period of time.

## **Disclaimers**

This report is subject to the Terms of Use ( <a href="https://www.ibm.com/legal/us/en/">https://www.ibm.com/legal/us/en/</a>) and the following disclaimers:

The information contained in this report is provided for informational purposes only. While efforts were made to verify the completeness and accuracy of the information contained in this publication, it is provided AS IS without warranty of any kind, express or implied, including but not limited to the implied warranties of merchantability, non-infringement, and fitness for a particular purpose. In addition, this information is based on IBM's current product plans and strategy, which are subject to change by IBM without notice. IBM shall not be responsible for any direct, incidental, consequential, special or other damages arising out of the use of, or otherwise related to, this report or any other materials. Nothing contained in this publication is intended to, nor shall have the effect of, creating any warranties or representations from IBM or its suppliers or licensors, or altering the terms and conditions of the applicable license agreement governing the use of IBM software.

References in this report to IBM products, programs, or services do not imply that they will be available in all countries in which IBM operates. Product release dates and/or capabilities referenced in this presentation may change at any time at IBM's sole discretion based on market opportunities or other factors, and are not intended to be a commitment to future product or feature availability in any way. The underlying database used to support these reports is refreshed on a weekly basis. Discrepancies found between reports generated using this web tool and other IBM documentation sources may or may not be attributed to different publish and refresh cycles for this tool and other sources. Nothing contained in this report is intended to, nor shall have the effect of, stating or implying that any activities undertaken by you will result in any specific sales, revenue growth, savings or other results. You assume sole responsibility for any results you obtain or decisions you make as a result of this report.

Notwithstanding the Terms of Use ( <a href="https://www.ibm.com/legal/us/en/">https://www.ibm.com/legal/us/en/</a>), users of this site are permitted to copy and save the reports generated from this tool for such users own internal business purpose. No other use shall be permitted.